


Introduction

Mellow Elephant is an collection of applications which use old radio scanners such as the [Uniden BC-780-XLT](#) (or similar) to create a database of spectrum utilization. The spectrum database is created by tuning the scanner and collecting the signal strength. Sampling continues for an extended period. Continuous emitters should be observed on every pass while transient emitters take awhile to discover.

Here is a sample graph from Mellow Elephant of my local FM broadcast band. The line w/ticks represent signal strength (and each tick is a sample), and the peak values represent active emitters. The continuous line represents a moving average signal strength.



I use a raspberry pi 3 to host Mellow Elephant and control a BC-780-XLT via RS-232 and a USB adapter. Here is a photo of the actual equipment.



Uniden BC-780-XLT

The BC-780-XLT was one of the earliest radio scanners to allow control by computer, in this case via [RS-232](#). Controlling the scanner is similar to the [Hayes command set](#) in that one writes a simple ASCII string to the device and then read the results. There is more about the BC-780-XLT command set near the end of this file.


There were several variations on the BC-780-XLT such as the Radio Shack PRO-2052, all w/similar behavior. Examples of the BC-780-XLT are readily available via eBay. The BC-780-XLT are mediocre receivers, and do suffer from poor intermods (in my case, harmonics from commercial FM broadcasters are a problem).

The BC-780-XLT defines chunks of spectrum into bands (table at end of file) which loosely map to spectrum service allocations. Mellow Elephant can be configured to search or ignore by Uniden band.

Getting Started

Ready to put an old radio to work? You will need a RS-232 cable and (probably) a USB to RS-232 converter. Here are some [cabling instructions](#).

If you like, you can reset a BC-780-XLT to factory settings by powering off, then holding down 2, 9 and "MAN" keys while powering on. The scanner will set the serial port to 9600, which is what Mellow Elephant uses.



Look at your scanner display. Do you see "RMT" (in the square)? If so, you are all ready for "Remote" mode. If not, press "E" for 2 seconds and "RMT" should appear.

With the radio configured, plug it into your USB port. Discover the USB assignment using dmesg (or similar) which will emit a message like:

```
usb 1-1.3: p12303 converter now attached to ttyUSB0
```

Which indicates your serial device is `"/dev/ttyUSB0"`.

Configure Mellow Elephant Application

1. You will need python3 to use Mellow Elephant, type 'which python3' to discover location.
2. Clone Mellow Elephant repository <https://github.com/guycole/mellow-elephant>

3. Create a python virtual environment

1. cd to the src directory and type 'virtualenv -p /usr/local/bin/python3 venv' where "/usr/local/bin/python3" is replaced by the actual location of python3 on your machine (from step 1).
 2. type 'source venv/bin/activate'
 3. type 'pip install -r requirements.ubuntu'
4. Now test interaction w/the radio.
1. cd to the bin directory
 2. Update "serialDevice" within "serial_test.yaml" to reflect your USB port assignment.
 3. Update "serial_test_usb0.sh" to reflect your actual path.
 4. Invoke "serial_test_usb0.sh" and if all goes well, the computer will ask BC-780-XLT for system information.

Prepare for Mellow Elephant Collection

Uniden divided coverage into various "bands" which I also use to manage frequencies of interest.

"Bands" don't actually map to spectrum service types, but there is some overlap. I provide a band table at the end of this file.

1. cd to the bin directory
1. Update "serialDevice" within "collect.yaml" to reflect your USB port assignment.
2. Update "collect_usb0.sh" to reflect your actual path.
3. Invoke "collect_usb0.sh" and the application should start collection, eventually producing a "pickled band file" in the "observations/fresh" directory.

Processing Collected Observations

Once you have created "pickled" band files, you can extract for database and graphs.

For simplicity, Mellow Elephant uses the sqlite3 database support that comes w/python and the graphs are created using gnuplot (which you might need to install). I have left some band files in "observations/fresh" as demonstration objects.

1. cd to the bin directory
1. Update the "processing.yaml" to reflect your own paths.
2. Update "processing.sh" to reflect your actual path.
3. Invoke "processing.sh" and the demonstration files will be processed.
1. sqlite3 database will be created (3x files in db directory)

2. Pickled band files will move from fresh to archive directory
3. New graph files will be created in the graphs directory

RS-232

Configure the scanner for speed 9600.

A complete command summary can be found at

<http://www.netfiles.ru/share/linked/fl/UnidenProtocol.pdf>)

Uniden Bands

Index	Band #	Lower	Upper	Increment	Modulation
1	1	25.0	26.96	5.0	AM
2	2	26.965	27.405	5.0	AM
3	3	27.41	27.995	5.0	AM
4	4	28.0	29.69	10.0	FM
5	5	29.7	49.99	10.0	FM
6	6	50.0	53.99	10.0	FM
7	7	54.0	71.95	50.0	WFM
8	8	72.0	75.995	5.0	FM
9	9	76.0	87.95	50.0	WFM
10	10	88.0	107.9	100.0	WFM
11	11	108.0	136.975	25.0	AM
12	12	137.0	143.995	5.0	FM
13	13	144.0	147.995	5.0	FM
14	14	148.0	161.995	5.0	FM
15	14	162.0	173.9875	12.5	FM
16	15	174.0	215.95	50.0	WFM
17	16	216.0	224.995	5.0	FM
18	17	225.0	399.95	50.0	AM
19	18	400.0	405.9875	12.5	NFM
20	19	406.0	419.9875	12.5	NFM
21	20	420.0	424.9875	12.5	NFM
22	20	425.0	429.9875	12.5	NFM
23	20	430.0	449.9875	12.5	NFM
24	21	450.0	454.9875	12.5	NFM
25	21	455.0	459.9875	12.5	NFM

26	21	460.0	464.9875	12.5	NFM
27	21	465.0	469.9875	12.5	NFM
28	22	470.0	472.9875	12.5	NFM
29	22	473.0	475.9875	12.5	NFM
30	22	476.0	478.9875	12.5	NFM
31	22	479.0	481.9875	12.5	NFM
32	22	482.0	484.9875	12.5	NFM
33	22	485.0	487.9875	12.5	NFM
34	22	488.0	490.9875	12.5	NFM
35	22	491.0	493.9875	12.5	NFM
36	22	494.0	496.9875	12.5	NFM
37	22	497.0	499.9875	12.5	NFM
38	22	500.0	502.9875	12.5	NFM
39	22	503.0	505.9875	12.5	NFM
40	22	506.0	508.9875	12.5	NFM
41	22	509.0	511.9875	12.5	NFM
42	23	806.0	823.9875	12.5	NFM
43	23	849.0125	850.9875	12.5	NFM
44	23	851.0	868.9875	12.5	NFM
45	23	894.0125	895.9875	12.5	NFM
46	23	896.0	901.0	12.5	NFM
47	23	901.0125	934.9875	12.5	NFM
48	23	935.0	940.0	12.5	NFM
49	23	940.0125	956.0	12.5	NFM
50	24	1240.0	1300.0	12.5	NFM